

NoiseAtWork V2024

Installation manual

Note: V2024 uses a new licensing method that does not need any online access for activation and deactivation. A license for V2024 can therefore not be used for V2023 or earlier versions

for the installation of V2023 and earlier versions see:

https://download.dgmrsoftware.nl/software/NAW/NAW2023_Installation_Manual.pdf

Content

1. System requirements	3
2. License types	4
3. Installation procedure	5
3.1 Uninstalling NoiseAtWork	6

1. System requirements

The minimum system requirements for using NoiseAtWork are:

- Operating system: Windows 10/11
- 30 Mb free disk space for project file (*.naw)
- Printer: MS Windows compatible printer

2. License types

NoiseAtWork is available in four types of licenses: workstation licenses, site licenses, company licenses and enterprise licenses. All licenses are rental licenses and will be valid only during the rental period. The current licensed period is shown in the lower right corner of the software interface and in the menu option 'Help | Info'.

Note: There is no auto renewal option for renewing licenses. This means that the Customer must purchase a new rental license before the current rental period expires. New rental licenses can be purchased in the web shop.

For price information see <https://dgmsoftware.com/products/noiseatwork/price-information-naw/>

Workstation license

A workstation license allows the use of the software on one dedicated PC only and is therefore bound to a desktop or laptop PC. The software will usually be installed on the local hard disk.

Site license

A site license allows the simultaneous use of the software on all computers of the company located at one specific address location.

Company license

A company license allows the simultaneous use of the software on all computers of the company within one country.

Enterprise license

An enterprise license allows the simultaneous use of the software on all computers of the company and its affiliates worldwide.

Demo mode

In case of no valid license, the software will run in Demo mode. This means that it can be used to evaluate the software before purchasing a license. In demo mode only the integrated demo project can be viewed and modified.

3. Installation procedure

Please note 1: the installation of NoiseAtWork and the license file has to be executed by a user with sufficient user rights (for instance an administrator).

Please note 2: The software can be installed on a local drive or on a network drive. However the permitted use of the software is depending on the purchased license. See the EULA. After installation of the software the file EULA.PDF is available in the installation folder.

After the purchase of a license you will receive installation instructions with a download link of the setup program and a valid license file 'dgmr.licx' by email from DGMR.

STEP 1: Installation of the software:

1. download the setup program and save it on your local hard drive or desktop
2. start the setup program
3. select the desired language in which the software will be installed
4. to continue installing, the End User License Agreement (EULA) has to be accepted
5. check if the installation folder is correct. If not, it can be changed here.
Note: In case of a Workstation license the software will usually be installed on the local hard disk. In case of a Site, Company or Enterprise license it is recommended to install the software on the network. After installation a shortcut to noiseatwork.exe can be created on each PC connected to the network

STEP 2: Installation of the license file 'dgmr.licx':

Option 1 - Recommended: In installation folder

1. Save the license file that is attached to the email on your desktop first.
2. Copy and paste, using CRTL-C (do not use Cut or CTRL-X) and CTRL-V, the license file from your desktop into the NoiseAtWork installation folder.

Option 2 - Alternative: In a shared folder as defined in the license.cfg file

1. Save the license file that is attached to the email on your desktop first.
2. Copy and paste, using CRTL-C (do not use Cut or CTRL-X) and CTRL-V, the license file from your desktop into a shared folder.
E.g. '\\DCDH3\Progs\AppsData\Licenties\' or 'P:\data\Licenses\'
3. The path to the shared folder location should be entered in the text file 'license.cfg' and should be stored in the installation folder. e.g. 'C:\Program Files\DGMR\NoiseAtWork V2024\license.cfg'. When starting NoiseAtWork the license.cfg file is read and NoiseAtWork will expect a valid dgmr.licx license file in the shared folder.

An example of a license.cfg file is given below:

[Location]

Path=\\DCDH3\Progs\AppsData\Licenties\

3.1 Uninstalling NoiseAtWork

NoiseAtWork can be uninstalled by opening the Windows control panel and starting “Programs and features” on the workstation or server on which it is installed.